

2.5.0 1

2.5.0

2017-09-25

- SEOS (Elite Key, RF)
- CoreStation
- Intrusion Alarm Zone
- Ethernet Zone
- USB Export 가
- 가

1. SEOS (Elite Key, RF) iClass SEOS

- [BS2_GetCardConfigEx](#) 가
- [BS2_SetCardConfigEx](#) 가
- [BS2CardConfigEx](#) 가

2. CoreStation Controller CoreStation Slave . CoreStation Master

Controller UI CoreStation BioStar

- [BS2_GetSlaveExDevice](#) 가
- [BS2_SetSlaveExDevice](#) 가
- [BS2Rs485SlaveDeviceEX](#) 가

3. Intrusion Alarm Zone

가 , , Video (biostar1.X) , 3rd party alarm / , Visual map

```
* [[BS2_GetIntrusionAlarmZone]] 가
* [[BS2_GetIntrusionAlarmZoneStatus]] 가
* [[BS2_SetIntrusionAlarmZone]] 가
* [[BS2_SetIntrusionAlarmZoneAlarm]] 가
* [[BS2_RemoveIntrusionAlarmZone]] 가
* [[BS2_SetIntrusionAlarmZoneArm]] 가
* [[Configuration API#BS2IntrusionAlarmZoneBlob]] 가
```

4. Ethernet Zone Zone Master BioStar V2.x 가 가
 (Master ↔ Member) Ethernet TCP Zone 1.x
 Entrance Limit, Fire Alarm Zone

- [BS2_GetDeviceZone](#) 가
- [BS2_SetDeviceZone](#) 가
- [BS2_RemoveDeviceZone](#) 가
- [BS2_SetDeviceZoneAlarm](#) 가
- [BS2DeviceZoneConfig](#) 가

5. USB Export USB
 Export / Import T&A () BioStar
 가 USB , USB
 T&A USB , USB

- [BS2_GetUserListFromDir](#) 가
- [BS2_GetUserInfosFromDir](#) 가
- [BS2_GetLogFromDir](#) 가

5. 가 SDK 가

* [BS2_GetFilteredLogSinceEventId](#) 가

3. BS2_ScanFingerprint BS2_ScanFingerprintEx 가가
 outQuality 가가

```
#include "BS_API.h"

int BS2_ScanFingerprintEx(void* context, uint32_t deviceId, BS2Fingerprint*
finger, uint32_t templateIndex, uint32_t quality, uint8_t templateFormat,
uint32_t* outQuality, OnReadyToScan ptrReadyToScan);
```

From:
<http://kb.supremainc.com/bs2sdk/> - **BioStar 2 Device SDK**
 Permanent link:
http://kb.supremainc.com/bs2sdk/doku.php?id=ko:release_note_250&rev=1508216212
 Last update: **2017/10/17 13:56**